# **DNA Preparation from Blood**

Section of Cancer Genomics, Genetics Branch, NCI National Institutes of Health

## Reagents

Ammonium chloride (NH<sub>4</sub>Cl)

Chloroform

Mallinckrodt, Cat. 4440

Ethanol, absolute

HCl

Isoamyl alcohol

Sigma, Cat. I-3643

**Isopropanol** (2-Propanol)

Phenol

Potassium carbonate (KHCO<sub>3)</sub>

Proteinase K

EM Science, Gibbstown, WV, Cat. 24568-2 (100 mg)

**Sodium** acetate

Sodium chloride

Sodium EDTA (Na<sub>2</sub>EDTA)

Sodium dodecyl sulfate (SDS 10%)

Digene Diagnostics, Inc, Cat. 3400-1016

Tris EDTA buffer, pH 8.0

# **Preparation**

Lysis Buffer

NH<sub>4</sub>Cl 8.29 g f.c. [155 mM] KHCO<sub>3</sub> 1 g f.c. [10 mM]

Fill to 1000 ml with distilled water

Adjust to pH 7.4 with 1 M HCl or NaOH for each use

## Chloroform/Isoamyl alcohol 24:1

Chloroform 24 ml Isoamylalcohol 1 ml

#### **SE-Buffer**

NaCl 4.39 g f.c. [75 mM]

Na<sub>2</sub>EDTA <u>8.41 g or 50 ml EDTA 0.5 M</u> f.c. [25 mM]

Fill to 1000 ml with distilled water

Adjust to pH 8.0 with 1 M NaOH for each use

#### Sodium acetate

3 M Sodium acetate 246 g/L Adjust to pH 5.2 with CH<sub>3</sub>COOH

### Proteinase K (10mg/ml)

Dissolve 100 mg Proteinase K in 10 ml TE for 30 min at room temperature Aliquot and store at  $-20^{\circ}$ C

### **Procedure**

- 1. To 10 ml whole blood (EDTA, heparin, citrate) add 30 ml lysis buffer, shake gently, incubate for 30 min on ice, and centrifuge at 1200 rpm for 10 min at 4° C.
- 2. Remove supernatant (blood waste), add 10 ml lysis buffer, resuspend the pellet, and centrifuge for 10 min at 4°C (1200 rpm).
- 3. Remove supernatant (blood waste), add 5 ml SE-buffer, resuspend the pellet, and centrifuge for 10 min at 4°C (1200 rpm).
- 4. Remove supernatant (blood waste). (It is possible to store the pellet at -80°C. To do so, add 1 ml SE-buffer and resuspend the pellet. Use a cryo-tube and centrifuge at 1200 rpm for 10 min at 4°C. Remove the supernatant and freeze the pellet.) Add 5 ml SE-buffer and resuspend the pellet, add 40 μl proteinase K (10 mg/ml) and 250 μl 20% SDS, shake gently, and incubate overnight at 37°C in a water bath.
- 5. Add 5 ml SE-buffer and 10 ml phenol, shake by hand for 10 min, and centrifuge at 3000 rpm for 5 min at 10°C.
- 6. Transfer the supernatant into a new tube, add 10 ml phenol/chloroform/isoamyl alcohol (25:24:1), shake by hand for 10 min, and centrifuge at 3000 rpm for 5 min at 10°C.

- 7. Again transfer the supernatant into a new tube, add 10 ml chloroform/isoamylalcohol (24:1), shake by hand for 10 min, and centrifuge at 3000 rpm for 5 min at 10°C.
- 8. Transfer the supernatant into a new tube, add 300 µl 3 M sodium acetate (pH 5.2) and 10 ml isopropanol, shake gently until the DNA precipitated, use a glass pipette, make a hook over a bunsen burner, and capture the DNA.
- 9. Wash the DNA in 70% ethanol and dissolve the DNA in 0.5-1 ml TE-buffer overnight at 4°C on a rotating shaker. (If the DNA is not dissolved leave it longer at 4°C on the rotating shaker).
- 10. Measure the DNA concentration in a spectrophotometer (Pharmacia, GeneQuant) and run 200 ng on a 1% agarose gel.